

READ ME - No536 USB Update Procedure

No536 USB UPDATE PROCEDURE

IMPORTANT NOTE: BEFORE ATTEMPTING AN UPDATE, PLEASE ENSURE THAT THE SERIAL NUMBER OF THE UNIT IS 1000 OR HIGHER. DO NOT ATTEMPT THIS UPDATE IF THE SERIAL NUMBER IS LOWER THAN 1000.

1. Turn off power to the No536 using the rear power switch.
2. Use a computer to download, extract/unzip, and copy the update files ("No536.s19" and "version.txt") to a USB flash drive (FAT32 format). Once copied, eject the flash drive from the computer and insert it into the USB port on the back of the No536.
3. Power up the No536 using the rear power switch. The unit will check the flash drive for the valid update files and proceed with the installation - the Standby LED will turn blue and flash during the update process (this can take several minutes).

IMPORTANT NOTE: DO NOT REMOVE THE USB DRIVE OR INTERRUPT POWER DURING THE UPDATE PROCESS.

4. When the update process is complete the unit will return to the standby mode (red standby LED slowly flashing). Turn off power to the No536 using the rear power switch then remove the USB drive.
5. Power the No536 on using the rear switch to resume normal operation. Press the standby button to bring the No536 out of Standby.

RELEASE NOTES

V1.17: Implemented manual standby mode selection feature (see related technical bulletin)